

# **greenhouse**

## **Version**

# Table of Contents

Contents:

<b>school_logging</b>	<b>5</b>
• ColoredFormatter	5
• ColoredLogger	6
• CriticalExitHandler	6
• parse_args()	6
<b>DatabaseOperations</b>	<b>7</b>
• DatabaseOperations	7
• parse_args()	9

# Welcome to Greenhouse's Documentation!

This is the documentation for the **Greenhouse** project. This project provides tools for monitoring and managing a greenhouse environment. It includes:

- A custom logging module ( *school\_logging* ) for flexible and colored logging.
- Functionality to process and store measurements in db ( *greenhouse/measurements2db.py* ).

# Installation

To install the Greenhouse project, follow these steps:

1. Clone the repository:

```
git clone <your_repository_url> #todo
```

2. Install the required packages:

```
pip install -r requirements.txt
```

# Usage Example

Here's a quick example of how to use the *ColoredLogger* from the *school\_logging* module:

```
from school_logging.log import ColoredLogger

log = ColoredLogger(__name__)
log.info("This is an informational message.")
```

## school\_logging

This module defines a custom logger class, *ColoredLogger*, that provides colored log output to the console. It uses ANSI escape codes to color the log messages based on their severity level (DEBUG, INFO, WARNING, ERROR, CRITICAL).

Additionally, the *ColoredLogger* is designed to terminate the program immediately when a message with a CRITICAL log level is emitted. This behavior is implemented by raising a custom exception, *CriticalError*, in the *critical()* method.

The module also includes a custom logging handler, *CriticalExitHandler*, which can be used as an alternative to raising an exception. This handler will terminate the program when a CRITICAL log message is received.

Usage:

```
from logger import ColoredLogger

# Create a logger instance log = ColoredLogger(__name__)

# Log messages with different levels log.debug("This is a debug message.")
log.info("This is an info message.") log.warning("This is a warning message.")
log.error("This is an error message.") log.critical("This is a critical message. The
program will terminate.")
```

The module can also be used directly as a script. In this case, it will parse command-line arguments to set the logging level and demonstrate the logger's usage.

```
class school_logging.log.ColoredFormatter ( fmt = None , datefmt = None , style = '%', colored :
bool = True ) [source]
    Bases: Formatter
```

`format ( record : LogRecord ) → str` [\[source\]](#)

Format the specified record as text.

The record's attribute dictionary is used as the operand to a string formatting operation which yields the returned string. Before formatting the dictionary, a couple of preparatory steps are carried out. The message attribute of the record is computed using `LogRecord.getMessage()`. If the formatting string uses the time (as determined by a call to `usesTime()`), `formatTime()` is called to format the event time. If there is exception information, it is formatted using `formatException()` and appended to the message.

`class school_logging.log. ColoredLogger ( name : str , verbose_level_str : str = 'INFO' )` [\[source\]](#)

Bases: `object`

A custom logger class that provides colored output and terminates the program on critical errors.

`critical ( msg : str , * args : Any , ** kwargs : Any ) → None` [\[source\]](#)

Logs a critical message and raises a `CriticalError`.

`debug ( msg : str , * args : Any , ** kwargs : Any ) → None` [\[source\]](#)

Logs a debug message.

`error ( msg : str , * args : Any , ** kwargs : Any ) → None` [\[source\]](#)

Logs an error message.

`info ( msg : str , * args : Any , ** kwargs : Any ) → None` [\[source\]](#)

Logs an info message.

`warning ( msg : str , * args : Any , ** kwargs : Any ) → None` [\[source\]](#)

Logs a warning message.

`class school_logging.log. CriticalExitHandler ( level = 0 )` [\[source\]](#)

Bases: `Handler`

Custom handler that terminates the program when a CRITICAL-level log is emitted.

`emit ( record : LogRecord ) → None` [\[source\]](#)

Handles the log record. If the record's level is CRITICAL or higher, terminates the program.

Parameters :

`record` ( *logging.LogRecord* ) – The log record.

`school_logging.log. parse_args ( ) → Namespace` [\[source\]](#)

Parses command-line arguments.

**Returns :**

The parsed arguments.

**Return type :**

argparse.Namespace

## DatabaseOperations

This module provides a set of operations for interacting with an SQLite database to store and manage sensor data, specifically temperature and humidity measurements. It includes functionalities to establish a database connection, create tables, save sensor readings, and retrieve the current time from an NTP server.

The module uses a *ColoredLogger* for logging messages, providing clear and color-coded output to the console. It is designed to be used as part of a larger application, such as a greenhouse monitoring system, where real-time sensor data needs to be logged and stored in a persistent manner.

**Classes:**

DatabaseOperations: Encapsulates the database operations.

**Functions:**

parse\_args: Parses command-line arguments.

**class** greenhouse.measurements2db. DatabaseOperations [\[source\]](#)

Bases: `object`

Provides methods to interact with an SQLite database.

This class encapsulates database operations such as creating a database, saving measurements, and handling the database connection. It is designed to work with an SQLite database and uses a *ColoredLogger* instance for logging.

**DATABASE\_FILE**

The path to the SQLite database file.

Type :

str

### log

Logger instance for logging messages.

Type :

ColoredLogger

### conn

Database connection object.

Type :

Optional[sqlite3.Connection]

**DATABASE\_FILE** : str = 'measurements.db'

**TIME\_SERVER** : str = '216.239.35.0'

close\_connection ( ) → None [source]

Closes the database connection.

connect\_to\_database ( ) → None [source]

Establishes a connection to the SQLite database.

create\_database ( ) → None [source]

Creates the database table if it doesn't exist.

get\_ntp\_time ( ip\_address : str ) → datetime | None [source]

Fetches the server time from the given IP address and converts it to the local time zone.

Parameters: ip\_address (str): The IP address of the NTP server.

Returns: datetime

print\_database ( ) → None [source]

Prints the contents of the 'measurements' table to the console without brackets, quotes, or other special characters.

read\_sensor ( ) → None [source]

Simulates reading sensors and returns temperature and humidity. #todo replace with real data

save\_measurement ( temp : str , hum : float ) → None [source]

Saves a measurement to the database.



Parameters :

- **sensor\_name** ( *str* ) – The name of the sensor.
- **value** ( *float* ) – The measured value.

**greenhouse.measurements2db.parse\_args ( ) → Namespace** [\[source\]](#)

Parses command-line arguments for the database operations script.

This function defines and parses the command-line arguments required to perform database operations. Modify the argument definitions as needed for your specific database operations.

Returns: argparse.Namespace: Parsed command-line arguments.

# Indices and tables

- [Index](#)
- [Module Index](#)
- [Search Page](#)

